

MacBook Air Printing

TROUBLESHOOTING

If you are having issues printing from your MacBook, do the following 3 steps first before adding new printers.

1. Verify that you are on MSD wifi network.
2. Open list of currently installed printers. (🍏 menu → System Preferences → Printers & Scanners)
3. Delete any printers that are not currently working. (select printer, click on the minus (-))


ADDING NEW PRINTERS

1. Download Driver Software (Once driver has been installed, it will remain on your Mac)

- Open the Software network drive from you Network Connections folder on your desktop
- Open folder "0000-Teacher-MacBook-Air"
- Open folder "00 PRINTER DRIVER DOWNLOADS"
- Find and select which drivers you need, drag and drop package to desktop and continue with install.
- ⊗ Canon has two different drivers depending on your MacOS for High Sierra or Mojave.

2. Adding Printer using IP Address (Repeat this process for any printer to add on available printers list)

- Open list of currently installed printers. (🍏 menu → System Preferences → Printers & Scanners)
- Click on the plus sign (+) to add and open IP tab
- Using the chart, fill in the following information



Address: Using the chart, find and enter the IP Address for the printer you'd like to add.

Protocol: Drop down and select "Line Printer Daemon - LPD"

Queue: Leave blank


Name: Type in the name of the printer

Location: Can leave blank or as is

Use: if specific printing software auto fills (Kyocera, HP or Canon) keep checked and click "Add" OR if anything else fills in, use the drop down menu and click on "Select Software..."

- From the Select Software window, Filter and search the driver name.
- Find and highlight the correct name, click OK to finish and Add.

That printer should be available in your printers list. Repeat steps as needed for each printer. Drivers only need to be installed once the first time.



Email TechSupport@mscfsd.org with questions or continued issues

HIGH SCHOOL PRINTERS			IMMS, WIS and CEPS PRINTERS		
PRINTER NAME	IP ADDRESS	DRIVER NAME	PRINTER NAME	IP ADDRESS	DRIVER NAME
DO-4200	172.20.5.101	HP Universal Printing PCL 6	IMMS-102-1025	172.23.5.106	Canon iR1020/1024/1025
DO-BUSINESS	172.20.6.106	Canon iR-ADV C5250/5255 UFR	IMMS-GUIDE	172.23.5.105	Kyocera FS-3920DN KX
DO-COLOR	172.20.6.103	Canon iR-ADV C5235/5240	IMMS-HALLWAY-1025	172.23.6.103	Canon iR1020/1024/1025
DO-COPYSS	172.20.6.102	Canon iR-ADV 6255/6265 PCL6	IMMS-LIB-COLOR	172.23.6.110	Kyocera FS-C5100DN
HS-146-3920	172.21.5.111	Kyocera FS-3920DN KX	IMMS-LOUNGE-BW	172.23.6.101	Canon iR-ADV 6275 PCL6
HS-148	172.21.5.104	HP Universal Printing PCL 5	IMMS-LOUNGE-COLOR	172.23.6.113	Canon iR-ADV C256/356 UFR
HS-170	172.21.5.105	HP Universal Printing PCL 5	IMMS-OFFICE	172.23.6.104	Canon iR-ADV 4225/4235
HS-171	172.21.5.106	HP Universal Printing PCL 5	IMMS-PLTW	172.23.5.104	HP Universal Printing PCL 5
HS-172	172.21.5.116	Kyocera ECOSYS P6035cdn KX	IMMS-UNIT6-BW	172.23.6.102	Canon iR-ADV 6275 PCL6
HS-204-COLOR	172.22.6.102	Canon iR-ADV C5235/5240	IMMS-UNIT7-COLOR	172.18.150.21	Canon iR-ADV C256/356 UFR
HS-216-CANON	172.22.6.101	Canon iR-ADV 6275 PCL6	IMMS-UNIT8-COLOR	172.23.6.111	Canon iR-ADV C256/356 UFR
HS-310-1025	172.22.6.103	Canon iR1020/1024/1025	WIS-1-BLUE-COLOR	172.24.6.110	Kyocera FS-C5100DN
HS-312-3920	172.22.6.106	Kyocera FS-3920DN KX	WIS-1-GREEN110A	172.24.5.102	HP Universal Printing PS
HS-AUTO	172.21.5.134	HP Universal Printing PCL 5	WIS-1-RED125	172.24.5.103	HP Universal Printing PS
HS-BANDROOM	172.20.6.107	Canon iR-ADV 400/500 PCL6	WIS-2-BLUE235	172.24.5.105	HP Universal Printing PS
HS-CADLAB-5000	172.21.5.101	HP Universal Printing PCL 6	WIS-2-COLOR-GREEN	172.24.5.107	Kyocera FS-C5150DN KX
HS-COPY1	172.21.6.101	Canon iR-ADV 8285/8295 PCL6	WIS-2-LAB	172.24.6.105	Kyocera FS-3920DN KX
HS-COPY2	172.21.6.102	Canon iR-ADV 8285/8295 PCL6	WIS-2-RED-COLOR	172.24.5.106	Kyocera FS-C5100DN KX
HS-FACE-BW	172.21.6.110	Kyocera FS-1370DN KX	WIS-LIB-1025	172.24.6.102	Canon iR1020/1024/1025
HS-FACE-COLOR	172.21.6.110	Kyocera FS-C5100DN KX	WIS-OFFICE-COLOR	172.24.6.106	Canon iR-ADV C256/356 UFR
HS-FOODS-1025	172.20.6.112	Canon iR1020/1024/1025	WIS-OFFICE-COPY1	172.24.6.101	Canon iR-ADV 6275 PCL6
HS-GUIDANCE	172.20.6.104	Canon iR1020/1024/1025	WIS-OFFICE-COPY2	172.24.6.103	Canon iR-ADV 6275 PCL6
HS-LB2	172.20.5.114	Kyocera FS-C5150DN KX	CEPS-1ST-WORKROOM	172.26.6.112	Canon iR-ADV 6255 PCL6
HS-LIB	172.20.5.115	Kyocera FS-C5150DN KX	CEPS-1ST-WORKRM-COLOR	172.26.6.113	Canon iR-ADV C256/356 UFR
HS-MAILROOM-4050	172.21.5.110	HP Universal Printing PCL 5	CEPS-2ND-WORKROOM	172.26.6.117	Canon iR-ADV 6255/6265
HS-OFFICE-CANON	172.20.6.105	Canon iR-ADV 6255/6265 PCL6	CEPS-2ND-WORKRM-COLOR	172.26.6.115	Canon iR-ADV C256/356 UFR
HS-OFFICE-COLOR	172.20.6.110	Kyocera FS-C5100DN KX	CEPS-K-WORKROOM	172.26.6.104	Canon iR-ADV 6275 PCL6
HS-SCHOOL-STORE	172.21.5.113	Kyocera FS-C5100DN KX	CEPS-K-WORKRM-COLOR	172.26.6.110	Kyocera FS-C5100DN
HS-SCIENCE-1025	172.22.5.105	Canon iR1020/1024/1025	CEPS-OFFICE-BW	172.26.6.105	Canon iR-ADV 400/500 PCL6
HS-TECHED-BW	172.21.6.111	Kyocera FS-1370DN KX	CEPS-OFFICE-COLOR	172.26.6.116	Canon iR-ADV C256/356 UFR
HS-TECHED-COLOR	172.21.6.111	Kyocera FS-C5100DN KX	CEPS-OFFICE-WORKROOM	172.26.6.111	Canon iR-ADV 6275 PCL 6
			CEPS-LIBRARY-COLOR	172.18.150.41	Canon iR-ADV C256/356 UFR